

Basic Memory Introduction

An introduction to low-level programming and how to avoid

```
$. /a.out  
105  
Core Dumped.
```

going over why it happens, How to diagnose compiled (C/C++) programs & how to fix it.

I wrote assuming the reader has experience in some garbage collected language like Python or Javascript.

[1] WHY

In many languages deemed high level or easy to use the main thing allowing this easy development without directly caring about the underlying memory & addresses is a garbage collector, on a very high level they work like this:

```

int func( ) {
    String x = "APPLE"; → "APPLE" allocated
    func2(x); → Copy of x made & tracked.
    x = "ORANGE"; → "APPLE" removed
                  & "ORANGE" allocated
}

```

This is a very rough example to give out an idea of its purpose, there are many different ways a garbage collector can function. See the working of the Java or the C# GC if you're interested in the engineering behind them.

<Talk about various GC strategies>

All in all, GCs are fantastic bits of engg. that make the vast majority of coding relatively hassle free by removing the need of the coder to manage memory.

But if you're reading this, you already decided you can't use one or for the following use cases might be suboptimal,

- Byte Wrangling: You're moving around a lot of

large buffers around & you can't afford any overhead in copying & in general want to interact with the bytes correctly.

- Latency sensitive code: What you're working on is real-time or cannot tolerate a GC pause at any time.
↓
microseconds your program's execution could be paused to free() objects.

- High Performance: This is a bad reason to choose after C, C++, Rust for, you can get fast code in all the languages but it's true that compiled languages tend to be closer to the hardware so can be optimized at a lower level.

*: Be careful of choosing a bad lang. simply b/c you think something like C# would be too slow, chances are good C# code can outperform the equivalent code in Rust (eg.).

It all depends on the algorithms & the data structures you employ.
↓
 $O(n)$

HOW

*

ov - oversimplified
for exple.
■ - Additional
comment

Primer

I'm going to over a few concepts here so that I can use the terms I'm comfortable with.

Byte → A collection of 8 bits. [uint8_t]

Slice / Span → A struct consisting of a ptr & a length (bytes).
↳ struct → A collection of multiple diff data types together.

Pointer → An offset into program memory, can encode the type of object its pointing to.

void*
↓
Anything

int*
↓
Integer(s)

Could point to multiple objects in sequence but you cant infer that from its type.

Program memory can be thought of a long (very long) tape where each slot in that tape can hold a byte (Byte addressable)



A pointer simply points to one of these bytes.

or

Heap / Stack:

You can think of this type as being divided into 2 kinds, A fast type w/ limited qty & one bulk cheap type but its slower.

The fast type is the Stack, the other is Heap


↓
Its already managed for you

↓
You manually manage this one.


Allocating / Freeing:

This mostly applies to the heap & not the stack since that one is already managed for you.

when you want to put say 500 numbers on the heap, you need a pointer to 500×4 bytes of free space, you can't simply point a pointer to any memory address that is not given to your program by the OS, so you have to humbly request the OS for these 2^3 bytes of free space, this process of asking for memory from the operating system is called allocation.



Please sir, may I have some more memory



The opposite process, returning the memory to the operating system (ie giving up ownership) is called freeing.

Segmentation Fault (SIG-SEV):

When your program tries to access memory it doesn't have access to, the OS kills the process & raises a segfault error.

String:

Since I'm mostly writing from the perspective of a C programmer, the string I will be referring to is a C-string.

"APPLE" →

A	P	P	L	E	\0
---	---	---	---	---	----

 ↑
 char* ptr

The string is stored w/ no length & is terminated with a NULL byte (\0)

Reverse

I feel the easiest way to go over will be to re-read common issues you could face & see what's going on & how to solve it.

Returning a stack string.

I specify stack since a heap pointer can be passed around till the pointer is freed.

Let's take the following:

```
1. char* getTimestampStr( ) {  
2.     char timestamp[100];  
3.     snprintf(timestamp, sizeof(timestamp), "%llu", time(NULL))
```

```
4. return timestamp;
5. }
```

In line 2, we declare a variable 'timestamp' to be 100 chars [notice theres no allocation so this a stack variable]

or In this cwe put the UNIX timestamp into that variable, → using sprintf()

sizeof(x) → Gives the size of a data type as known at compile time, Not useful for pointers since it'll return the no of bytes to store the pointer (8 bytes)

If you replace the data type of timestamp w/ this you'll get 8 also → `sizeof ((char*)timestamp);`

↓
Casting away the known array type.

Then after insertion, the function returns the variable as a pointer.

↓
C doesn't have proper 'ARRAY' types so any array is fundamentally a pointer to memory.

But this will fail since the pointer returned by the function will be invalid. This will be easiest to show with the assembly:

The following ASM is for AMD64 (sysv calling convention)


getTimestampStr:

```
push rbp → Store callee address on stack
• 1 sub rsp, 112 → Reserve 100 bytes on the stack
xor edi, edi → Zero out EDI register
call time@PLT → Call time(EDI=0)
lea rdi, [rip + .L.str] → Store &"%llu"
• 2 mov rbp, rsp → Store address of stack space
mov esi, 100 → Store sizeof(timestamp)
mov rdi, rbp → Copy buffer address
mov rcx, rax → Store output of time(NULL)
xor eax, eax → Mark as multiple variadic arguments
call snprintf@PLT → Call snprintf(rdi, rsi, rcx, rcx)
mov rax, rbp → RAX = RBX = Buffer pointer.
• 3 add rsp, 112 → "Unreserve" stack space
pop rbp → Restore callee address
ret
```

If you haven't messed w/ assembly registers, here's what you need to understand

Stack (Data Structure)

Think of a stack of plates.



(plates)

You can push new elements to the end of the stack

You can only pop the last inserted element → i.e. the element at the top of the stack.

[WikiBook Link](#)

The CPU Stack (from w/h we derive stack memory from) is basically some scratch space (think like a rough notebook) whenever it needs some memory & It can't use its registers (insufficient space/data to be stored for later); So stack memory really refers to data stored on this stack.

The CPU has a stack register (ESP) & instructions only for pushing & popping data from the stack.

Pushing data increments the SP


Popping data decrements the SP

Now we can look at the instructions,

- 1 → This reserves 112 bytes of space on the stack (112 → 100 + rounding to 16b boundary)
- 2 → Sets the address of the array to the current stack pointer address.
- 3 → Unreserves the stack space (cleanup).

I hope the problem is very visible now, the stack space isn't reserved at all so any future code that modifies the stack could clobber the char array so corrupting our string → Makes the returned pointer pointless.

There's 3 ways we can solve this, you should've thought of 1 already,



Once you're done, you'll start to notice almost all C APIs using (B) or (C) in order to pass non primitive data back to the caller.

(A) This is done by marking the array static

```
10 .LC0:
11     .string "%llu"
12     .text
13     .globl getTimestampStr
14     .type getTimestampStr, @function
15 getTimestampStr:
16     endbr64
17     push    rbx #
18     # t.c:6: snprintf(timestamp, sizeof(timestamp), "%llu", time(NULL));
19     mov     edi, 0 #,
20     call    time@PLT #
21     mov     r9, rax # tmp86,
22     # /usr/include/x86_64-linux-gnu/bits/stdio2.h:54: return __builtin___snprintf_chk(__s, __n, __USE_FORTIFY_LEVEL,
23     lea     r8, .LC0[rip] #,
24     mov     ecx, 100 #,
25     mov     edx, 2 #,
26     mov     esi, 100 #,
27     lea     rbx, timestamp.0[rip] # tmp84 → Function static storage
28     mov     rdi, rbx #, tmp84
29     mov     eax, 0 #,
30     call    __snprintf_chk@PLT #
31     # t.c:8: }
32     mov     rax, rbx #, tmp84
33     pop     rbx #
34     ret
35     .section .getTimestampStr, ".getTimestampStr"
36     .local timestamp.0
37     .comm    timestamp.0, 100, 32
38     .section .note.GNU-stack,"",@progbits
39     .section .note.gnu.property,"a"
40     .align 8
41     .long    if - 0f
42     .long    4f - 1f
43     .long    5
```

} The "%llu" local

} Reserve space for static variable.

The main problem w/ this approach is that you control it on-demand.

The storage is attached to this storage so if you did this.

getTimestampStr()

↳ Stores "T+0" in static variable space & returns pointer to it

getTimestamp()

↳ Stores "T+1" in static variable

Direct output from GCC

Also this is impractical for large objects like several megabytes in size. Its best for singletons or for function returns that are expected to be used then discarded before the next function call.

After the 2nd call, the first functions output is removed/replaced.

⑧ This is done by manually allocating memory & manually freeing it.

Say you have an object w/ some more or known size, & the size is > than say 4kB (4096 bytes), It's a good candidate to be heap allocated, It's also really useful if the object size could change in the future / it needs to be passed around

In our example, we have a 'timestamp' array, that we're determined to be more 100 bytes ^(100s) in size, we can get a pointer to 100 bytes of space on the heap using `malloc()`

`char* timestamp = (char*) malloc(sizeof(char) * 100);`

Notice that we can no longer keep the array size w/ its type since the compiler is unaware of what `malloc()` is doing, It only knows it will return a `void*` pointer.

So it's up to us to make sure we are always in bounds of our heap variables or we can run into segfault.

So since `sizeof(timestamp)` no longer knows the size of our array, we have to hardcode it.

`snprintf(timestamp, 100, "%llu", time(NULL));`

For this reason of often associating the size of our obtained pointer it's very common to see a struct like this:

```
struct slice_t {  
    void* ptr;  
    size_t len;  
}
```

↳ The correctly sized int type to hold any possible memory size

This is very often used type in Zig or other languages.

Once we are done using the heap memory object, It's common to free() it. This returns the memory to the OS for further use.

If you continually allocate memory without freeing it, that's called a memory leak & eventually the system won't allocate any more memory (OOM)

`free(timestamp);`

Remember to only call `free()` once after the memory is used. If you call `free()` again on an already freed variable that's a double free error.
The pointer that is freed is no longer valid after its freed, using a freed variable will cause a use after free error or a segfault

If you want to resize the block given by `malloc()` use `realloc()`

`timestamp = realloc(timestamp, 2000);`

↓
timestamp is now 2kb.
Original data preserved.

- ③ This is a way of simply not making it your problem, you make it the caller's responsibility to allocate & give you a large enough buffer which can be either heap or stack allocated.

The function can be changed to

```
void getTimestampStr(char* buf, size_t buf-s) {  
    sprintf(buf, buf-s, "%llu", time(NULL));  
}
```

& it could be called like this

```
int main() {  
    char ts[100];  
    getTimestampStr(ts, sizeof(ts));  
}
```

```
int main() {  
    char ts* = (char*) malloc(1024);  
    getTimestampStr(ts, 1024);  
}
```

STACK


HEAP

This one is best if you want the buffer size to be configurable or if the function directly writes to a byte array.

DEBUGGING INTRODUCTION

Even following best practices, you can very easily catch a segfault & it will make you a lot more confident if you can triage / diagnose & remedy it.

The diagnosis & remedy will depend on your specific project but I can show you some ways to triage issues.



-faddress = sanitizers

This compiler flag enables the address sanitizer or ASAN, how it works isn't exactly relevant but you can think of it like this:

Write to invalid
memory address
↓
segfault
occurs
↓
O/S detects
write & signals
SIGSEGV

Write to invalid
memory address
↓
Caught by ASAN
↓
Prints detailed information
w/ stack trace

So when your program crashes,
you get a nice helpful message

